

# Connect to UNT Wi-Fi with Android

Different Android versions and phone brands (Samsung, Google Pixel, Motorola, etc.) may label options slightly differently, but the steps below apply to all modern Android devices.


---

## 1. Open Wi-Fi Settings

1. Swipe down from the top of the screen.
  2. Tap the **Wi-Fi** icon 
- OR**
- Tap the **gear icon** → **Network & internet** → **Wi-Fi**.
- 

## 2. Select the “UNT” Network

1. Ensure Wi-Fi is **turned on**.
2. In the list of networks, tap **UNT**.



### 3. Configure UNT as follows:

You should see several fields. Use the following settings:

- **EAP method:** PEAP
- **Phase 2 authentication:** MSCHAPV2
- **CA certificate:** Do not validate **OR** Use system certificate
- **Domain:** *unt.edu* **OR** *untsystem.edu*
- **Identity:** Your UNT EUID
- **Anonymous identity:** *(Leave blank)*
- **Password:** Your UNT EUID Password

The screenshot shows a configuration dialog box titled "UNT". It contains several fields and options:

- EAP method:** A dropdown menu with "PEAP" selected.
- Phase 2 authentication:** A dropdown menu with "MSCHAPV2" selected.
- CA certificate:** A dropdown menu with "Do not validate" selected.
- Identity:** A text input field containing "Scrappy".
- Anonymous identity:** An empty text input field.
- Password:** A password input field with masked characters (dots).
- Show password:** An unchecked checkbox.
- Advanced options:** A dropdown arrow.
- Buttons:** "Cancel" and "Save" buttons at the bottom.

A warning message is displayed below the CA certificate field: "No certificate specified. Your connection will not be private."

---

### 4. Connect

1. Double-check your entries.
2. Tap **Connect**.

Your device should authenticate and join the network.

---

## 5. Verify Connection

Once connected, you'll see:

- A **Wi-Fi icon**  in the status bar
  - **"Connected"** displayed under the UNT network
- 

## 6. If You Cannot Connect: Forget the Network and Try Again

If your Android device refuses your password, keeps looping back to the login screen, or won't join the network, clearing the saved Wi-Fi configuration usually fixes the issue.

---

### Forget the UNT Network

1. Open **Settings** → **Network & Internet** → **Wi-Fi**  
(Some devices may show **Connections** → **Wi-Fi**)
  2. Find **UNT** in the list of saved or available networks.
  3. Tap and hold **UNT**, or tap the **gear/settings icon** next to it.
  4. Select **Forget** (or **Forget Network**).
- 

### Restart the Login Process

1. Toggle **Wi-Fi Off**, then turn it **On** again.
2. Select **UNT** from the Wi-Fi list.
3. Re-enter your:
  - **EUID username**
  - **EUID password**
4. Accept or **Trust the certificate** if your device prompts you.

This process removes cached credentials and outdated security settings, resolving most authentication and connection issues.